

### **Manual**

### Software SI-COLO3-Scope V6.4

(PC software for Microsoft® Windows® Vista, XP, 2000, NT® 4.0, Me, 98, 95)

## for color sensors of SI-COLO3 Series with internal temperature compensation and white light balancing

This manual describes the installation of the PC software for the SI-COLO3 color sensor. As a support for commissioning of the color sensor this manual explains the functional elements of the Windows® user interface.

The SI-COLO3 color sensor detects the radiation that is diffusely reflected by the target. The SI-COLO3 color sensor uses a white-light LED with adjustable power as a light source. A triple receiver for the RED, GREEN, and BLUE content of the light reflected from the target is used as a receiver. With the stepless adjustment of the integrated light source and the selectable gain of the receiver signal the sensor can be set to almost any surface.

The SI-COLO3 color sensor can be "taught" up to 15 colors. Tolerances can be set for every taught color. In X/Y INT or s/i M mode the tolerances represent a color cylinder in space. In X/Y/INT or s/i/M mode the tolerance represents a color sphere in space. Color evaluation according to s/i M and s/i/M uses the Lab calculation method. All the modes can be used in combination with various operating modes, among others "FIRST HIT" and "BEST HIT". The raw data are represented with 12 bit resolution.

Color detection either operates continuously or is started by means of an external SPC trigger signal. The respective detected color either is output as binary code at the 4 digital outputs, or it can be sent directly to the outputs, if only up to 4 colors are to be detected. Simultaneously the detected color code is visualised at the SI-COLO3 housing by means of 4 LEDs.

With the TEACH button at the sensor housing the sensor can be taught up to 15 colors. For this purpose the corresponding evaluation mode must be set with the software. The TEACH button is connected in parallel to the input IN0 (green wire of cable cab-las8/SPS).

Through the RS232 interface parameters and measured values can be exchanged between the PC and the SI-COLO3 color sensor. All the parameters for color detection can be stored in the non-volatile EEPROM of the SI-COLO3 color sensor. When parameterization is finished the color sensor continues to operate with the current parameters in "stand alone" mode without a PC.

The sensors of the SI-COLO3 V6.4 series can be calibrated (white light balancing). Balancing can be performed to any white surface. A ColorChecker<sup>™</sup> table with 24 color fields according to CIE standard is available as an alternative, and white light balancing or calibration can then be performed to one of the white fields.



### 0 Contents

		Page
1.	Install	ation of the SI-COLO3-Scope software3
2.	Opera	tion of the SI-COLO3-Scope software4
	2.1	Tab CONNECT
	2.2	Tab PARA, button SEND, GET, GO, STOP (parameterization, data exchange)7
	2.3	Tab TEACH TABLE
	2.4	Tab TABLE ATTRIBUTES21
	2.5	Tab GROUPS23
	2.6	Tab RECORDER21
	2.7 2.7.1 2.7.2	Tab CALIBRATE       25         White light balancing       25         Offset calibration       28
	2.8	Graphic display elements
3.	Short	instructions for the operation of color sensors with the SI-COLO3-Scope V6.4 software31
4.	Opera	tion of the TEMPCOMP-Scope V1.0 software
5.	Exterr	al triggering of the SI-COLO3 color sensors
6.	Functi	on of the LED display
7.	Conne	ector assignment of the SI-COLO3 color sensors40
8.	RS232	2 communication protocol

Shortcuts	5:
SEND GET GO STOP	F9 F10 F11 F12



### **1** Installation of the SI-COLO3-Scope software

Hardware requirements for successful installation of the SI-COLO3-Scope software:

- IBM PC AT or compatible
- VGA graphics
- Microsoft® Windows® Vista, XP, Me, 2000, NT® 4.0, 98, or 95
- Serial RS232 interface at the PC
- Microsoft-compatible mouse
- Cable for the RS232 interface
- CD-ROM drive
- Approx. 5 MByte of free hard disk space

The SI-COLO3-Scope software can only be installed under Windows. Windows must therefore be started first, if it is not yet running.

Please install the software as described below:

1.	The software can be installed directly from the installation CD-ROM. To install the software, start the SETUP program in the INSTALL folder of the CD-ROM.
2.	The installation program displays a dialog and suggests to install the software in the C:\"FILENAME" directory on the hard disk. You may accept this suggestion with <b>OK</b> or [ <b>ENTER</b> ], or you may change the path as desired. Installation is then performed automatically.
3.	During the installation process a new program group for the software is created in the Windows Program Manager. In the program group an icon for starting the software is created automatically. When installation is successfully completed the installation program displays "Setup OK".
4.	After successful installation the software can be started with a left mouse button double-click on the icon.

Windows® is a trademark of the Microsoft Corp.  $VGA^{TM}$  is a trademark of the International Business Machines Corp.



### 2 Operation of the SI-COLO3-Scope software

Please read this chapter first before you start to adjust and parameterize the SI-COLO3 color sensor.

#### Pressing the right mouse button on an individual element will call up a short help text.

When the SI-COLO3-Scope software is started, the following window appears on the Windows interface:

SI-COLO3-SCOPE V6.4							
SI-COLO3-Scope V6.4							
CONNECT PARA TEACH TABLE GROUPS RECORDER CALIBRATE TABLE ATTRIBUTES POWER MODE STATIC POWER (pm) 100	SOURCE × 0 Y	X/Y INT     TEMP     0       10000- 9000- 8000-					
0 500 1000 0''N WIN LO 3000 DYN WIN HI 3800 AVERAGE 4096 V	INT 0	7000- 6000- 5000-					
INTEGRAL 1 MAXCOL-No. 1 OUTMODE DIRECT HI INTLIM 0 HOLD [ms] 10	delta C -1 C-No: 0	4000-					
EVALUATION MODE BEST HIT CALCULATION MODE X/Y INT CALCULATION MODE X/Y INT CALCULATION MODE X/Y INT CALCULATION MODE RAM SEND GO		0- 0 2000 4000 6000 8000 10000 • 0 500 1000 1500 2000 2500 3000 3500 4096					
		IP ADDRESS 192.168.3.150 SI-COLO3 V6.4 RT:KW34/09					

### 2.1 Tab CONNECT

#### CONNECT

COMMUNICATION PROTOCOL	RS232 -
SELECT COM PORT [1256]	1
SELECT BAUDRATE	19200 🔽
TRY TO CONNECT	r
FIRMWARE STRING	
ACCEPT SETTINGS CHANC	AUDRATE
INSERT A PANEL ID	
COMMUNICATION PROTOCOL	
IP ADRESS (xxx.xxx.xxx.xxx) OR	
▼ 192.168.3.15	1
PORT NUMBER (Default 10001)	10001

#### CONNECT:

Pressing the **CONNECT** tab opens a window for selecting and configuring the interface.

The **COMMUNICATION PROTOCOL** function field is used for selecting either an **RS232** or a **TCP/IP** protocol.

If **RS232** is selected, a port from 1 to 256 can be selected with **SELECT COM PORT**, depending on which port the sensor is connected to.

The sensor operates with a set baudrate that can be modified with **CHANGE BAUDRATE** (see below). The sensor and the user interface both must operate with the same baudrate. At the user interface the baudrate is set with **SELECT BAUDRATE**. If after starting the software should not automatically establish a connection, the correct baudrate can be found with **SELECT BAUDRATE**.

If an adaptor is used, the **COM PORT** number can be determined by way of the hardware manager in the system control panel.

If the sensor should communicate through a local area network, an RS232 to Ethernet adaptor will be needed. This adapter makes it possible to establish a connection to the sensor with the **TCP/IP** protocol.


The network adaptors that are available from us are based on the Lantronix XPort module. For parameterising these adapters (assigning of an IP address, setting of the Baud rate of 19200) please download the "DeviceInstaller" software that is provided free of charge by Lantronix at <u>http://www.lantronix.com/</u>. DeviceInstaller is based on Microsoft's ".NET" framework. Detailed operating instructions for the "DeviceInstaller" software also are available from Lantronix.

In order to establish a connection to the adaptor, its IP address or HOST name must be entered in the field **IP ADRESS (xxx.xxx.xxx) OR HOST NAME**. The DROP DOWN menu (down arrow) shows the last 10 IP addresses that were used. An address from this list can be directly selected by clicking on the respective item. The DROP DOWN list is saved and is thus always available when the software is closed.

The **PORT NUMBER** for the XPort-based network adaptors is 10001. This port number must not be changed.

When you press the **TRY TO CONNECT** button, the software tries to establish a connection with the set parameters. The communication status is shown in the display field. If the sensor answers with its FIRMWARE ID, the set connection type can be accepted by pressing **ACCEPT SETTINGS**. You will then be returned to the **PARA** tab. If you get a **TIMEOUT** message, the software could not establish a connection to the sensor. In this case please check if the interface cable is correctly connected, if the sensor is supplied with power, and if the set parameters are correct.

If a connection has been accepted by pressing **ACCEPT SETTINGS**, the software starts automatically with these settings when called the next time.





COMMUNICATION PROTOCOL RS232 🔽 SELECT COM PORT [1...256] 1 SELECT BAUDRATE 19200 🔻 TRY TO CONNECT FIRMWARE STRING ACCEPT SETTINGS CHANGE BAUDRATE

The baudrate for data transfer through the RS232 interface can be set by means of the SELECT BAUDRATE drop down menu and CHANGE BAUDRATE function field.

This is necessary if a high-speed connection is needed for data transfer through the serial interface.

If the baudrate should be changed, a connection must first be established by clicking on TRY TO CONNECT. The CHANGE BAUDRATE button will then be active.

COMMUNICATION PROTOCOL	RS232 🗸
SELECT COM PORT [1256]	1
SELECT BAUDRATE	19200 🔽
<b>F</b>	
TRY TO CONNEC	т
TRY TO CONNEC	T

COMMUNICATION PROTOCOL	RS232 🕶
SELECT COM PORT [1256]	1
SELECT BAUDRATE	115200 🔽
TRY TO CONNEC	T I
TRY TO CONNEC	T

COMMUNICATION PROTOCOL	RS232 🔽
SELECT COM PORT [1256]	1
SELECT BAUDRATE	115200 💌
1	
TRY TO CONNEC	T I
TRY TO CONNEC	T



When the new baudrate information has been successfully sent, the sensor operates with the new baudrate. A window will pop up, prompting you to select EEPROM and then to press SEND. After a hardware reset the new baudrate only will be used when EEPROM and SEND have been pressed.

A click on ACCEPT SETTINGS saves the current interface settings, which will then be automatically set when the software is restarted.

Now a new baudrate can be selected under SELECT BAUDRATE. A click on CHANGE BAUDRATE sends the new baudrate information to the sensor.



### 2.2 Tab PARA, button SEND, GET, GO, STOP

CONNECT PARA TEACH TABLE GROUPS						
RECORDER CALIBRATE TABLE ATTRIBUTES						
POWER MODE STATIC						
POWER (pm)						
0500 1000						
0''N WIN LO 3000 EYN WIN HI 3500						
AVERAGE 4096						
INTEGRAL 1						
MAXCOL-No. 3						
OUTMODE DIRECT HI						
INTLIM 0						
HOLD [ms] 10						
EVALUATION MODE BEST HIT						
CALCULATION MODE X/Y INT						
EXTEACH OFF TRIGGER CONT						
RAM SEND GO						
FILE GET STOP						

#### PARA:

Pressing the **PARA** tab opens a window for setting the sensor parameters.

#### ATTENTION!

A change of the parameter function groups only becomes effective at the sensor after actuation of the SEND button in the MEM function field!

#### SEND [F9]:

When the **SEND** button is clicked (or shortcut key button F9 is pressed), all the currently set parameters are transferred between PC and sensor. The target of the respective parameter transfer is determined by the selected button (**RAM**, **EEPROM**, or **FILE**).

#### GET [F10]:

The currently set values can be interrogated from the sensor by clicking on the **GET** button (or with shortcut key button F10). The source of data exchange is determined by the selected button (**RAM**, **EEPROM**, or **FILE**).

#### RAM:

After a click on the **SEND** button the current parameters are written into the **RAM** memory of the sensor, or they are read from the **RAM** by clicking on the **GET** button, i.e. these parameters are lost when the voltage at the sensor is switched off.

#### EEPROM:

After a click on the **SEND** button the current parameters are written into the non-volatile memory of the **EEPROM** in the sensor, or they are read from the **EEPROM** by clicking on the **GET** button, i.e. the parameters in the internal **EEPROM** are stored when the voltage at the sensor is switched off.

#### FILE:

After pressing **SEND**, the current parameters can be written to a selectable file on the hard disk. With **GET** parameters can be read from such a file. When the **SEND** or **GET** button is pressed, a dialog box opens for selecting the desired file.

#### GO [F11]:

A click on this button (or with shortcut key button F11) starts data transfer from the sensor to the PC through the serial RS232 interface.

**SOURCE** is used to select which signals should be shown in the displays and graphs.

#### STOP [F12]:

A click on this button (or with shortcut key button F12) stops data transfer from the sensor to the PC through the serial RS232 interface.



EVALUATION MODE	FIRST HIT
	✓ FIRST HIT
	BEST HIT
	MIN DIST
ļ	COL4


EVALUATION MODE:

This function field serves for setting the evaluation mode at the SI-COLO3 color sensor.

All the evaluation modes apply to all CALCULATION MODE = X/Y INT, s/i M, X/Y/INT and i/i/M. The TEACH TABLE is correspondingly adapted depending on the CALCULATION MODE. The following explanation uses CALCULATION MODE = X/Y INT

EVALUATION MODE	FIRST HIT	T
-----------------	-----------	---

						_
	X	Y	СТО	INT	ITO	4
0	2354	903	100	1555	100	1
1	2354	903	200	1555	200	т
2	2354	903	300	1555	300	Т
3	2354	903	400	1555	400	
4	1	1	1	1	1	
E	1	1	1	1	1	



#### FIRST HIT:

The currently measured color values are compared with the default values in the TEACH TABLE, starting with teachcolor 0. If in the row-by-row comparison the current color values correspond with the teach-parameters entered in the TEACH TABLE, this first "hit" in the TEACH TABLE is displayed as a color number (C-No.) and is output at the digital outputs (OUT0 ... OUT3) according to the settings of the OUTMODE parameter (see OUTMODE).

If the current color does not correspond with any of the teach-colors, the color code C-No. = 255 will be set ("error status").

**Tip!** This mode is used if only one color is taught, and this color must be checked to avoid "drifting away". With the rising tolerance windows this can be detected very well, and countermeasures can be initiated, if necessary.

**Tip!** If, for example, only the X/Y coordinates should be checked, and intensity INT is of no importance, a tolerance of 4000 can be selected for ITO. This inspection criterion is thus always fulfilled.


**Tip!** Values can be entered in a cell of the table either by double-clicking on the respective cell, or by highlighting the respective cell and then pressing F2.

**Tip!** The teach colors are only activated when the SEND button is pressed!

Sensor Let's make sensors more individual



						 _
	X	Y	СТО	INT	ITO	4
0	2364	894	200	1580	200	1
1	1379	1700	200	1112	200	L
2	1120	1084	200	1127	200	Т
3	1	1	1	1	1	



#### **BEST HIT:**

The currently measured color values are compared with the default values in the TEACH TABLE, starting with teachcolor 0. If in the row-by-row comparison the current color values correspond with several of the teach parameters entered in the color table, the teach parameter that has the shortest x/y distance from the current color value will be a hit.

This "hit" in the TEACH TABLE is displayed as a color number (C-No.) and is output at the digital outputs (OUT0 ... OUT3) according to the settings of the OUTMODE parameter (see OUTMODE).

If the current color does not correspond with any of the teach-in colors, the color code C-No. = 255 will be set ("error status").

**Tip!** This mode is used if several colors must be separated from each other, and only certain surface fluctuations are allowed.


**Tip!** Since what you are looking for here with several "hits" is the shortest distance of the current color to the centres of the taught colors, the individual tolerance windows (circles) may overlap here. The sensor detects the "**best hit**".

**Tip!** Values can be entered in a cell of the table either by double-clicking on the respective cell, or by highlighting the respective cell and then pressing F2.

**Tip!** In CALCULATION MODE = X/Y/INT or s/i/M the shortest distance in a three-dimensional space is calculated.

**Tip!** The teach colors are only activated when the SEND button is pressed!

Sensor Let's make sensors more individual



#### MIN DIST:

The individual teach-in colors defined in the TEACH TABLE are present as points in the color triangle, defined by their (X,Y) value pairs. When this evaluation mode is set at the SI-COLO3 color sensor, the evaluation algorithm, starting from the currently measured color value (X,Y), calculates the distance to the individual teach-in colors in the color triangle. The current color value (X,Y) is assigned to the teach-in color that is closest in the color triangle.

It is furthermore checked whether the intensity condition for this color also is true. If the intensity condition is not true, the second shortest distance will be checked, etc.

The color detected this way is output at the digital outputs (OUT0 ... OUT3) according to the settings of the OUTMODE parameter (see OUTMODE).

C-No. will only be set to 255, if the current intensity falls below the value set under INTLIM (see INTLIM).

#### Comment:

The value of 40 is only entered here in order to be able to represent the coordinates of the individual teach colours in the graph. It has no meaning for evaluation.

**Tip!** This mode is used if you have taught several surfaces of separate colors, and a current color in any case must be assigned to one of the taught colors. This applies, for example, if you want to compensate a product variation, or if you have to solve sorting tasks.

**Tip!** If, for example, only the X/Y coordinates should be checked, and intensity INT is of no importance, a tolerance of 4000 can be selected for ITO. This inspection criterion is thus always fulfilled.

**Tip!** Values can be entered in a cell of the table either by double-clicking on the respective cell, or by highlighting the respective cell and then pressing F2.

**Tip!** In CALCULATION MODE = X/Y/INT or s/i/M the shortest distance in a three-dimensional space is calculated. **Tip!** The teach colors are only activated when the SEND button is pressed!

EVALUATION MODE	COL4 V	<b>COL4:</b> In this evaluation mode the rows 0 to 3 in the TEACH TABLE are evaluated.
0		Every match of current vector (row number) and teach vector is directly sent to the corresponding output. Example.
<ul><li>1</li><li>2</li></ul>		If the result of evaluation is that both row 0 and row 3 is a hit, outputs OUT0 and OUT3 will be set to high (+24V).
<b>9</b> 3		<b>Tip!</b> If the result of evaluation is that both row 0 and row 3 are hits, outputs OUT0 and OUT3 will be set to high (+24V).
		<b>Tip!</b> Values can be entered in a cell of the table either by double-clicking on the respective cell, or by highlighting the respective cell and then pressing F2.
		<b>Tip!</b> The teach vectors are only activated when the SEND button is pressed!

Attention! In COL4 evaluation mode it is not possible to form color groups!

		Sensor We Let's make sensors more individual
		<b>Instruments</b>
CALCULATION MODE	XAY INT	CALCULATION MODE:

#### X/Y INT:

The X/Y pairs of the individual red, green, and blue components, and the intensity are used for evaluation. For X/Y a color tolerance CTO can be set, and for the intensity an INT tolerance ITO can be set. With the individual tolerances the color is represented as a cylinder in space (see picture below). CTO defines the diameter of the cylinder, and ITO the height of the cylinder.

#### s/i M:

The s/i pairs of the individual red, green, and blue components, and M are calculated for evaluation. This calculation method follows the Lab calculation method. For s/i a color tolerance siTO can be set, and for the intensity an M tolerance MTO can be set. With the individual tolerances the color is represented as a cylinder in space (see picture below). siTO defines the diameter of the cylinder, and MTO the height of the cylinder. X/Y/INT:

For evaluation, X, Y, and INT are calculated from the individual red, green, and blue components. These three values define a point in three-dimensional space. The tolerance value that is entered defines a sphere in space with radius TOL (see picture below).

#### s/i/M:

For evaluation, s, i, and M are calculated from the individual red, green, and blue components following the Lab calculation method. These three values define a point in three-dimensional space. The tolerance value that is entered defines a sphere in space with radius TOL (see picture below).

#### Calculation of coordinates:

Х X-value of the taught color (in the color triangle numerical value on the x-axis: RED color content) R \* 4095 s

$$X = \frac{1}{R+G+B}$$

s is calculated on the basis of the Lab color evaluation method.

Y-value of the taught color (in the color triangle numerical value on the y-axis: GREEN color content) Y i V \_ \* 4095 B


$$R + G + g$$

i is calculated on the basis of the Lab color evaluation method.

M 
$$INT = \frac{R+G+B}{3}$$

M is calculated on the basis of the Lab color evaluation method.

- СТО In CALCULATION MODE = X/Y INT or s/i M, CTO or siTO is the color tolerance radius around the respective taught X/Y or s/i pair. CTO or siTO defines the radius of the color cylinder in space. Within siTO the thus defined "tolerance circle" the current color is recognised as the taught color.
- ITO In CALCULATION MODE = X/Y INT or s/i M, ITO or MTO is the intensity tolerance window around the respective taught intensity INT or M. ITO or MTO defines the height of the color cylinder in MTO space. Within the thus defined "tolerance window" the current color is recognised as the taught color.
- In CALCULATION MODE = X/Y/INT or s/i/M, TOL is the tolerance radius around the respective TOL taught point X/Y/INT or s/i/M in space. TOL defines the radius of the color sphere in space. Within this sphere the current color is recognised as the taught color.





POWER MODE STATIC
POWER (pm) 0
DYN WIN LO 3000 DYN WIN HI 3500

#### POWER MODE:

In this function field the operating mode of automatic power correction at the transmitter unit (transmitter LED) can be set.

**STATIC:** The transmitter power is constantly kept at the value set with the **POWER** slider (recommended operation mode).

**DYNAMIC:** The LED transmitter power is dynamically controlled in accordance with the amount of radiation that is diffusely reflected from the object. By using the intensities measured at the receivers the automatic control circuit attempts to adjust the transmitter power in such a way that the dynamic range, which is determined by **DYN WIN LO** and **DYN WIN HI**, is not exceeded.

**POWER [pm]:** In this function field the intensity of the transmitter LED can be adjusted by using the slider or by entering a value in the edit box. A value of 1000 means full intensity at the transmitter LED, a value of 0 stands for the lowest transmitter intensity adjustment!

**INFO:** The **POWER** slider is only effective in the **POWER MODE = STATIC**. **DYN WIN LO** and **DYN WIN HI** are only effective in **POWER MODE = DYNAMIC**.

AVERAGE	1	-
INTEGRAL	1	

#### AVERAGE:

This function field is used for adjusting the number of scanning values (measurement values) over which the raw signal measured at the receiver is averaged. A higher **AVERAGE** default value reduces noise of the raw signals at the receiver unit and there will be a decrease of the maximal available switching frequency of the sensor.

#### **INTEGRAL:**

This function field is used to set the number of scan values (measurement values) over which the raw signal measured at the receiver is summed up. This integral function allows the reliable detection even of extremely weak signals. A higher **INTEGRAL** value increases the noise of the raw signals of the receiver unit, and simultaneously decreases the maximum achievable switching frequency of the sensor.



#### TRIGGER:

This function field serves for setting the trigger mode at the SI-COLO3 color sensor. If TRIGGER is not CONT, the TRIG LED shows a trigger event.

Sensor

Let's make sensors more individual

Instruments

#### CONT:

Continuous color detection (no trigger event required).

#### SELF:

TRIG

By selecting SELF the sensor can be operated in self-trigger mode. The "free status" must be taught to row 0. With a split optical fibre in transmitted-light operation the free status, for example, is the uncovered status. In reflected-light operation the free status is the status when there is no part. Color detection is started when row 0 is no longer detected (self-trigger). After the trigger, i.e. when color 0 is detected again, the color from the taught colors will be output that was detected most frequently during triggering.

#### EXT1:

Color detection is started through the external trigger input (IN0 pin3 green of cable cab-las8/SPS) or by means of a click on the TEACH button. A trigger event is recognized as long as +24V is present at the IN0 input (HIGHactive). After the trigger input goes to LOW again, the state (color no.) that was last detected will be held at the outputs.

#### EXT2:

Same behaviour as in EXT1 mode, with the difference that an error state (color no. = 255) will be output after the trigger input goes to LOW again.

#### EXT3:

Color detection is started through the external trigger input (IN0 Pin3 grn at cable cab-las8/SPS) or by pressing the TEACH button. After triggering the color from the taught colors will be output that was detected most frequently during triggering.

#### EXT4:

Same behaviour as in EXT1. However, in contrast to EXT1 in this mode the transmitter source will be switched off if no trigger event (IN0 or TEACH button) is given.



#### EXTEACH:

In all the evaluation modes teaching of a color can be performed externally through INO or by means of the button at the sensor housing.

OFF: The external TEACH feature is deactivated. ON: See below

#### STAT1:

In static power mode, a color is taught to position 0 in the TEACH TABLE.

The POWER MODE is automatically set to STATIC. A fixed transmitter poser must be set with the POWER slider. When the button at the sensor housing is pressed, or after a positive signal (+24V) at input IN0, the current color is taught to row 0.

#### DYN1:

In dynamic power mode, a color is taught to position 0 in the TEACH TABLE, and evaluation is then performed statically.

The POWER MODE is automatically set to STATIC. When the button at the sensor housing is pressed, or after a positive signal (+24V) at input IN0, the transmitter power is set such that the sensor is in the dynamic range, which is defined by DYN WIN LO and DYN WIN HI. The current color is then taught to position 0 in the TEACH TABLE. The sensor then continues to operate statically with the established POWER value.

The taught color is stored only in the RAM and not in the EEPROM of the sensor.



Through IN0 or by way of the button at the sensor housing, the sensor can be taught up to 15 colors.

In EVALUATION MODE = FIRST HIT the currently present color is taught to all active rows depending on MAXCOL-No.

In EVALUATION MODE = BEST HIT, MIN DIST, and COL4 a single row in the TEACH TABLE can be selected with the teach button or through IN0.


The example shows the external teaching of 4 colors in EVALUATION MODE = BEST HIT.

Select the EXTERN TEACH = ON function.

Adjust the power value such that the sensor is neither overloaded nor that a too low signal arrives at the sensor. Select how many colors you wish to teach from extern.

Click on the TEACH TABLE tab to switch to the TEACH TABLE.

Then enter the corresponding tolerances for the colors you want to teach.



In this example, MAXCOL-No. = 4 was selected, i.e. the sensor should detect the color information that is stored in the first 4 rows of the TEACH TABLE by means of external teaching through INO. Since the sensor cannot calculate the tolerances for color circle (CTO) and intensity (ITO) itself, these values must be entered once only (in this case 200 at all places) and must be stored in the EEPROM (see above) together with the MAXCOL-No. and with EXTEACH = ON.

Sensor

Let's make sensors more individual

Instruments

Now select the setting EEPROM in the function field, and then click on SEND.

From now on, the PC is no longer necessary, as long as you only wish to teach colors up to the MAXCOL-No. and do not want to change the tolerances.

#### INFO:

Of course the taught colours can be viewed at any time with the PC.

Colors that are taught by way of EXTEACH = ON are stored in the EEPROM of the sensor, i.e. the information will <u>not</u> be lost when the system is turned off.

This function rather is intended for "after-teaching", because the sensor does not automatically adjust its POWER value.




Before the external teach-process can be started, the color to be taught must be presented to the sensor. The external teach process is started with a positive edge at IN0 (green wire). When such a positive edge is applied, the output LEDs (OUT0 ... OUT3) start to blink. From now on, the user has a certain number of seconds time to inform the sensor about the position at which the color information (X,Y,INT) should be placed in the TEACH TABLE. The period of time, in which the user can teach the color information to the sensor depends on the value that is set in MAXCOL-No. (e.g. approx. 5 seconds when MAXCOL-No. = 5).

The first positive edge (start edge 0) selects position 0 in the TEACH TABLE. Every additional positive edge selects one position higher (see table below).

#### Example:

If you wish to save the current color to position 3 in the TEACH TABLE, the following steps have to be performed:

- 1. Start of the external TEACH process with a positive edge (0) at IN0 → Position 0 is selected, the LEDs start to blink.
- 2. An additional positive edge (1) selects position 1 in the TEACH TABLE. This position 1 is indicated by the LEDs. The LED with binary value 1 remains on HIGH level all the time, while the other 3 LEDs continue to blink.
- 3. An additional positive edge (2) selects position 2 in the TEACH TABLE. This position 2 is indicated by the LEDs. The LED with binary value 2 remains on HIGH level all the time, while the other 3 LEDs continue to blink.
- 4. An additional positive edge (3) selects position 3 in the TEACH TABLE. This position 3 is indicated by the LEDs. The LEDs with binary value 3 remain on HIGH level all the time, while the other 2 LEDs continue to blink.
- 5. The desired position is now selected.
- 6. When the BUSY window is over (the LEDs stop to blink), the sensor starts the evaluation.
- 7. To teach another color  $\rightarrow$  go to pos. 1





INTLIM	100

#### INTLIM:

This edit box is used for setting an intensity limit. Color evaluation is stopped, if the current intensity INT arriving at the receiver unit falls below this limit, and ERROR STATE is output.

#### Attention: ERROR STATE if: INT < INTLIM

AXCOL-No. 1
-------------

#### MAXCOL-No.:

This function field serves for setting the number of colors to be checked.

In the BINARY mode the maximum number of colors to be checked is 15. In the DIRECT HI or DIRECT LO mode the maximum number of colors to be checked is 4 (colors no. 0, 1, 2, 3). The numerical value set here determines the currently possible scanning rate of the color sensor. The less the colors to be checked, the faster the operation of the SI-COLO3 color sensor.

The numerical value set here refers to the number of rows (starting with row 0) in the TEACH TABLE ( $\rightarrow$  2.3 Tab TEACH TABLE).

OUTMODE	BINARY	

#### OUTMODE:

This group of buttons offers the method of how to control the 4 digital outputs.

#### **BINARY:**

If in this row-by-row comparison the current color values correspond with the teach-in parameters entered in the TEACH TABLE, this color in the TEACH TABLE is displayed as a color number (C-No.) and is sent to the digital outputs (OUT0 ... OUT3) as a bit pattern. The maximum number of colors to be taught is 15.

#### DIRECT:

In this mode the maximum number of colors to be taught is 4.

If in this row-by-row comparison the current color values correspond with the teach-in parameters entered in the TEACH TABLE, this color in the color teach table is displayed as a color number (C-No.) and is sent **direct** to the digital outputs (OUT0 ... OUT3).

#### DIRECT HI:

If DIRECT HI is activated, the specially digital output is set to HI. If the current color does not correspond with any of the teach-in colors, all digital outputs are set to LOW (no LED is lighting).

#### DIRECT LO:

If DIRECT LO is activated, the specially digital output is set to LO, while the other ones are set to HI. If the current color does not correspond with any of the teach-in colors, all digital outputs are set to HIGH (all LEDs are lighting).

HOLD [ms]	0	<b>•</b>

#### HOLD:

The SI-COLO3 color sensor operates with minimum scanning times in the magnitude of less than 150 $\mu$ s. This is why most of the PLCs that are connected to the digital outputs OUT0 ...

OUT3 have difficulties with the safe detection of the resulting short switching state changes. For the digital outputs of the SI-COLO3 color sensor pulse lengthening of up to 100 ms can be set by selecting the corresponding HOLD value.



#### 2.3 **Tab TEACH TABLE**

When the GO button is pressed, data transfer from the sensor to the PC is started. The respective RED, GREEN, and BLUE contents are shown by way of the bars beside the graph. The calculated X, Y, INT or s,i,M values are visualised in the displays.

₩ SI-COLO3-SCOPE V6.4			
SI-COLO3-Scope V6.4			
X       Y       CTO       INT       ITO       2208         0       2208       994       200       1709       200       934         1       1280       1735       200       120       200       934         2       1148       1107       200       1503       200       934         2       1148       1107       200       1503       200       934         4       1218       1421       200       2907       200       1709         5       1737       1333       200       1464       200       6       1455       1729       200       1780       200         6       1455       1729       200       1780       200       1709       delta C         3       1395       1382       200       3957       200       10       1	XY INT       TEMP       36         2123- 2000- 1900- 1900- 1800- 1700- 1800- 1200- 100- 100- 1		



#### X or s:

This numerical value output field displays the RED content (x-axis) of the scattered light currently arriving at the receiver.



### Y or i:

This numerical value output field displays the GREEN content (y-axis) of the scattered light currently arriving at the receiver.

#### INT or M:

This numerical value output field displays the currently measured intensity (proportional to the average of the intensities at the triple receiver).

C-No:

#### C-No.:

This numerical value output field displays the currently detected color number in accordance with the entry in the TEACH TABLE. The currently detected color number is sent to the digital outputs OUT0 ... OUT3 as a corresponding bit pattern.

The value 255 means that none of the taught colors is recognised.

A double-click on the display opens a larger display window.

Please note:	The above-mentioned output fields are only updated when data transfer between PC
	and SI-COLO3 color sensor is active (GO button pressed).

Sensor	Let's make sensors more individual
Inst	truments

J	CONNECT PARA TEACH TABLE GROUPS							
В	RECORDER CALIBRATE TABLE ATTRIBUTES							
		X	Y	СТО	INT	ITO	_ ÷	
	0	2354	903	200	1555	200		
	1	1378	1702	200	1121	200		
	2	1126	1080	200	1114	200		
	3	1746	1563	200	2878	200		
	4	1289	1425	200	2269	200		
	5	1897	1257	200	1336	200		
	6	1569	1659	200	1663	200		
	7	1494	1170	200	2347	200		
	8	1543	1295	200	417	200		
	9	1471	1366	200	3566	200		
	10	1	1	1	1	1		
	11	1	1	1	1	1		
	12	1	1	1	1	1	T	
	TEA	CH DAT	ГА ТО	No			nc 🔳	
	TEACH MEAN VALUES							
	APPLY FROM ALL RESET TABLE							
	RAM SEND GO EEPROM GET STOP							

TEACH TABLE:

TEACH TABLE opens a view where colors can be taught to the TEACH TABLE.

### Please note: The sensor must be informed about the teach colors by pressing SEND.

After a left mouse button double click (or a click on shortcut key button F2) on the respective field the default values can be changed by entering numerical values with the PC keyboard.

The TEACH TABLE is organized in rows, i.e. the individual parameters for the teach-in colors are arranged side by side in the respective row.

The SI-COLO3 color sensor is able to check up to 15 teach-in colors. The number of the respective teach-in color is given in the left column of the table.

Only the green rows are used for evaluation in the sensor. The number of rows to be inspected is set with MAXCOL-No. .


When **TEACH DATA TO** is pressed, the currently displayed data for X, Y, INT or s, i, M are transferred to the row in the TEACH TABLE that is selected under **No.**:

A Color Tolerance (CTO) and an Intensity Tolerance (ITO) also are set. If necessary, these tolerances, as well as the teach values, can be changed as described above.

No.: also is used to select which INT or M tolerance window is shown in the respective graphs for the intensity or for M.

When Inc is activated, and the **TEACH DATA TO** button is pressed, the No.: input field is automatically incremented (increased) by 1, i.e. the next row in the TEACH TABLE is selected

A click on the **RESET TABLE** button resets the TEACH TABLE (RESET value = 1)



#### APPLY FROM ALL:

If X/Y or s/i is selected under SOURCE, a click on this button displays all the teach-in colors entered in the TEACH TABLE in the color triangle with the corresponding "tolerance circle" (radius = CTO or siTO).

The opposite picture shows 10 color tolerance circles with the teach-in values (X,Y) and CTO (tolerance radius) preset in the TEACH TABLE.



The following panel will be displayed after a click on TEACH MEAN VALUES.

The Teach Panel can be used in every EVALUATION and CALCULATION MODE. The explanation herein uses the EVALUATION MODE=BEST HIT and the CALCULATION MODE=X/Y INT.

🗮 TEACH PANEL								
CAPTURE COUNTER 6		R	G	В	X	Y	INT	4
	1	1909	1717	2814	1213	1091	2146	
UNDO RESET TABLE	2	1909	1717	2814	1213	1091	2146	
	3	1920	1726	2823	1215	1092	2156	
	4	1920	1726	2823	1215	1092	2156	
TEACH CTO WITH VALUE CTO	5	1904	1712	2807	1213	1091	2141	
VALUE CTO 100	6	1908	1717	2813	1213	1092	2146	
	7	0	0	0	0	0	0	
TEACH ITO WITH VALUE ITO	8	0	0	0	0	0	0	
VALUE ITO 100	9	0	0	0	0	0	0	
	10	0	0	0	0	0	0	Ŧ
		_	_	_				
TEACH TO TABLE ROW No.:		R	G	В	X	Y	INT	
	MEAN	1911	1719	2815	1213	1091	2148	
CLOSE TEACH PANEL	۸×) b	n 📕	2		d IN1		8	

The main panel remains active, and data are automatically picked up from the sensor and are displayed. A click on the **CAPTURE** button enters a parameter frame in the table.

The **COUNTER** display field shown how many frames have already been recorded.

The last frames that were entered in the table can be deleted again by pressing **UNDO**.

**RESET TABLE** sets the whole table back to 0.

After every activation of **CAPTURE**, **UNDO**, or **RESET TABLE**, the mean values for the individual parameters are calculated automatically and are displayed in the mean value table.

Furthermore, a maximum color deviation **d(X/Y)** and a maximum intensity deviation **dINT** for the average values will be formed.

When the **TEACH TO TABLE** button is pressed, the respective mean values are taught to the row in the **TEACH TABLE** that is selected under **ROW No.:** ( $\rightarrow$  2.3 Tab TEACH TABLE).


Teaching of the circular tolerance and of the intensity tolerance can be set by way of **TEACH CTO WITH** and **TEACH ITO WITH**, respectively.

- If the setting is VALUE CTO, the value that is set under VALUE CTO will be taught (ditto intensity).
- If the setting is d(X/Y), the value that is determined under d(X/Y) will be taught (ditto intensity).
- If the setting is **d**(X/Y) + VALUE CTO, the value that is determined under **d**(X/Y) plus VALUE CTO will be taught (ditto intensity).
- With NO CHANGE, the value that is set in the TEACH TABLE will remain unchanged.

A click on the **CLOSE TEACH PANEL** button will take you back to the main panel.

### 2.4 Tab TABLE ATTRIBUTES

CONNECT PARA TEACH TABLE GROUPS								
RECO	RECORDER CALIBRATE TABLE ATTRIBUTES							
SET	SET ROW COLORS MANUALLY							
	ECT ROW 🗐 0							
SELE								
A	SSIGN TO ROW	GET FROM FI	LE					
	SAVE TO FILE	SET AS STARTU	P FILE					
	SPECIFICATION							
0	Color 0							
1	Color 1							
2	Color 2							
3	Color 3							
4	Color 4							
5	5 Color 5							
6								
7	Color 7							
8								
9	Color 9							
10	Color 10							





#### TABLE ATTRIBUTES:

A click on **TABLE ATTRIBUTES** opens a panel where the row color in which the individual tolerance circuits are represented can be individually chosen or these can be automatically replaced by the color detected by the system.

Furthermore, designations for the individual rows can be entered in the **SPECIFICATION** table. These designations are saved on the PC's hard disk and can be loaded again, if necessary.

If **SET ROW COLORS** is set to **MANUALLY**, the row color that should be changed must be set under **SELECT ROW**.

A click on the colored area of **ROW COLOR** opens a color palette where the desired color can be selected.

After a click on the **ASSIGN TO ROW** button, the color will be displayed in the 6th column and the selected row of the **TEACH TABLE**.

If **SET ROW COLORS** is set to **AUTOMATICALLY**, the system will automatically calculate the corresponding row color, display the color in a color display beside the graph and, after a click on **TEACH DATA TO**, automatically insert it in the corresponding row.

The **SAVE TO FILE** and **GET FROM FILE** functions allow you to save specified row color arrays and the **SPECIFICATION** table on the hard disk, or to load previously saved arrays.

**SET AS STARTUP FILE** saves the current settings as startup array.

When the software is restarted, the corresponding **ROW COLOR** table as well as the **SPECIFICATION** table are automatically loaded from the startup array and displayed in the respective fields.



### 2.5 Tab GROUPS

CONNECT PARA TEACH TABLE GROUPS							
RECORDER CALIBRATE TABLE ATTRIBUTES							
	GROUP						
0	0						
1	0						
2	1						
3	1						
4	2						
5	0						
6	0	_					
7	0						
8	0						
9	0						
10	0						
11	0						
12	12 0						
13 0							
14	0	<b>T</b>					
🔳 BAM	SEND G						

# RAM SEND GO EEPROM GET STOP

### C-No: 3 GRP

#### GROUPS:

GROUPS opens a view where colors in the TEACH TABLE can be assigned to certain groups.

### Please note: The sensor must be informed about the color groups by pressing SEND.

It is possible to form color groups in evaluation modes **FIRST HIT**, **BEST HIT**, and **MIN DIST**. This means that in a special table the individual rows are assigned to a group

In this example, **COLOR GROUPS** has been set to **ON**, i.e. group evaluation is activated.

Rows 0 and 1 have been assigned to group 0.

Rows 2 and 3 have been assigned to group 1, and row 4 to group 2.

A **GRP** display is shown under the **C-No:** display.

If, as in this example, row 3 is detected in the evaluation, this row and the corresponding group will be visualised.

The group number will be output through outputs OUT0 to OUT3.

In evaluation mode **DIRECT HI** and **DIRECT LO** 15 different colors can be taught. However, a maximum of only 4 groups can be formed (group 0 to group 3).

A maximum of 15 groups (group 0 to group 30) can be formed in evaluation mode **BINARY**.

All the cell values can be set to 0 by pressing **RESET**.

A double-click on the **GRP** display opens a larger display window.

### 2.6 Tab RECORDER

The SI-COLO3-Scope software features a data recorder that allows the saving of RED, GREEN, BLUE, X, Y, INT, C-No: and TEMP. The recorded file is saved to the hard disk of the PC and can then be evaluated with a spreadsheet program.

The file that is created has eight columns and as many rows as data frames were recorded. A row is structured as follows: Date and time, RED, GREEN, BLUE, X, Y, INT, C-No:, TEMP.

The following steps describe how data frames are recorded with the recorder:

#### Please note:

Recording depends on the EVALUATION MODE that is chosen. Several EVALUATION MODES do not need certain data, therefore these data will be set to 0, i.e. for these data the value 0 will be recorded.

Step 1:

When the RECORDER button is pressed, the following window will be displayed:

When the SHOW GRAPH button is pressed, a panel will be displayed that allows the user to monitor the different signals.

The individual signals can be activated from the SIGNAL drop-down menu.

-** SI-COLO3-SCOPE V6.4						
SI-COLO3-Scope V6.4						
CONNECT PARA TEACH TABLE GROUPS	SIGNAL RED GRN BLUE X Y INT TEN RED 0 0 0 0 0 0					
RECORD MODE AUTO LIMITED  RECORD-TIME INTERVAL [sec] 1 RECORD VALUES (MAX 50 000) 1000	3801 - 3601 - 3401 - 3201 - 3001 -					
TOTAL RECORD TIME (days hours min sec)       0     0       16     40       RECORDED     REMAINING       0     1000	2801					
START RECORD STOP RECORD	1801 -					
SELECT RECORD FILE SHOW GRAPH ersion64\SiColo3V64\RecordFile.dat	1001 - 801 - 601 - 401 -					
RAM     SEND     GO       EEPROM     GET     STOP		90 100				



RECORD MODE					
RECORD-TIME INTERVA					
TOTAL RECORD TIME ( 0 0 RECORDED 0	days hours min sec) 16 40 REMAINING 1000				
START RECORD	STOP RECORD				
, SELECT RECORD FILE Filename	SELECT RECORD FILE SHOW GRAPH				

#### Step 2:

If you want to automatically record several data frames, please select **AUTO LIMITED** under **RECORD MORE**. Enter a time interval for recording under **RECORD-TIME INTERVAL [sec]**, in this example: 1, i.e. a new value is called from the sensor every second). Then enter the maximum number of values you wish to record in the **RECORD VALUES [MAX 50 000]** field. Please note: Recording can also be stopped earlier by clicking **STOP RECORD**, the data recorded so far will not be lost.

The **TOTAL RECORD TIME** field indicates how long recording will take (in days, hours, minutes, and seconds) if all data are recorded.

#### Step 3:

By pressing the button **SELECT RECORD FILE** a file can be selected in which the data frame will be stored. If you select an already existing file name, you will be asked whether you want to overwrite the existing file or not.

#### Step 4:

Pressing the START RECORD button starts automatic data recording.

The recorder starts to record data, and the button **START RECORD** is red to indicate that recording is active. The respective data frames are shown in the display windows.

In the two display fields **RECORDED** and **REMAINING** you can check how many data frames have been recorded, and how many frames remain to be recorded.

#### Please note:

During recording the two input fields RECORD-TIME INTERVAL and VALUES TO BE RECORDED are inactive.

#### Step 5:

When as many data frames as set under **RECORD VALUES** [MAX 50 000] have been recorded, or when the **STOP AUTO RECORD** button is pressed, a pop-up window will appear which confirms that the file is stored.

If you want to record an unlimited number of data, select the **AUTO UNLIMITED** function under **RECORD MORE**. Then select the desired recording interval and press **START RECORD**.

If you want to record data "manually", select the **MANUAL RECORDING** function under **RECORD MORE**. You can start reading data from the sensor by pressing the **GO** button. These data are visualised in the display window. Pressing the **CAPTURE DATA FRAME** button saves a data frame in the file that was selected under **SELECT RECORD FILE**. The **RECORDED** field shows the sum of the frames already recorded.

If AUTO TRIGGERED is selected under RECORD MORE, and TRIGGER = SELF, EXT1, EXT2, EXT3, or EXT4 is selected, the sensor will automatically send a data frame after each drop of the trigger when START RECORD is pressed. This data frame is captured and recorded by the recorder. Pressing the STOP RECORD button terminates the automatic sending function of the sensor again.

#### Please note:

When you press START RECORD, the file that is selected under SELECT RECORD FILE will be deleted. With RECORD FRAME MANUALLY, the file will be created if it does not already exist. If the file already exists, the data are added to the existing file.

### 2.7 Tab CALIBRATE

### 2.7.1 White light balancing

White light balancing can be performed with the sensors of the SI-COLO3 series. Balancing can be performed to any white surface. A ColorChecker<sup>TM</sup> table with 24 color fields according to CIE standard is available as an alternative, and white light balancing or calibration can then be performed to one of the white fields

The following panel will be displayed after a click on CALIBRATE:


SI-COLO3-SCOPE V6.4		
\$	SI-COLO3-Scope V6.4	
CONNECT PARA TEACH TABLE GROUPS RECORDER CALIBRATE TABLE ATTRIBUTES RED GREEN BLUE DELTA 0 0 0 0 0 MAX DELTA OF RAW DATA 500 SETVALUE FOR R,G, B 3000 CALC CALIB FACTORS CF_RED 1024 CF_GREEN 1024 CF_BLUE 1024	SOURCE       X/TINT         X       10000-         9000-       9000-         Y       8000-         0       6000-         0       6000-         0       6000-         4000-       -         4000-       -         0       5000-         5000-       -         0       6000-         5000-       -         0       6000-         10       000-         0       1000-	
SEND CF GET CF GET CF GET CF GET CF GET CF GET CF GO GO STOP	• o 500 1000 1500 2000 2500 3000 3500	10000 4096 RT:KW34/09

#### Calculation example for determining the calibration factors

In the example in the picture below, a POWER value at which the three bars of the raw signals **RAW DATA** are in the dynamic range has been set. Each of the three bars is at approx. 3600 digits. It is thus appropriate to set a setpoint value of 3600 (see **SETVALUE FOR R,G,B**) for the three bars. When calibration is now started by pressing CALCULATE CALIBRATION FACTORS, the software automatically calculates the calibration factors for channel RED, channel GREEN, and channel BLUE. The calibration factors are normalized as integers to the value 1024.

Formula:

```
CF_RED = (SETVALUE / RAW DATA RED) * 1024 = (3000 / 2913) * 1024 = 1056
CF_GREEN = (SETVALUE / RAW DATA GREEN) * 1024 = (3000 / 3081) * 1024 = 999
CF_BLUE = (SETVALUE / RAW DATA BLUE) * 1024 = (3000 / 3213) * 1024 = 956
```



When the calibration factors have been calculated by the software on the user interface, they are automatically saved to the non-volatile **EEPROM** memory of the sensor. Calibration is then finished, work can then be continued in the main panel.


When the sensor detects a raw signal, it applies the calibration factor saved in the **EEPROM** to this raw signal, i.e. in the main panel only the calibrated data for the RED, GREEN, and BLUE channels are displayed. Evaluation by the micro-controller also is exclusively done with the calibrated data.



#### In the following the individual steps for calibrating the sensors are described:

INFO: The individual pop-up windows are intended as a help to guide you through the calibration process.

ATTENTION: It is a prerequisite for successful calibration that the sensor front-end is calibrated to a white surface.



#### Step 1:

First of all a suitable **POWER** value must be found such that the **RAW DATA** for RED, GREEN and BLUE lie in the dynamic range (upper third of the bar display).

#### Step 2:

When you have set a suitable POWER value, determine a **SETVALUE FOR R,G,B**. The software now calculates the calibration factors in such a way that this SETVALUE is reached for the raw data (see calculation example above).

#### Step 3:

Determine a **MAX DELTA OF RAW DATA** (the software suggests 250).

Calibration is only permitted, if the current **DELTA** of the **RAW DATA** is smaller than the **MAX DELTA OF RAW DATA**.

**DELTA** is the maximum of **RED**, **GREEN**, and **BLUE**, minus the minimum of **RED**, **GREEN**, and **BLUE**. This is necessary in order to ensure that the sensor functions properly and calibration is performed on a white surface.

#### Step 4:

Start calibration by pressing CALC CALIB FACTORS.

The button starts to flash in red, and at the same time 100 raw data are recorded through the interface, of which the respective mean value of **RED**, **GREEN**, and **BLUE** is formed.

The individual calibration factors are formed from these mean values and from the **SETVALUES FOR R,G,B** and they are then entered in the corresponding edit-boxes.

The calibration software automatically saves the calculated calibration factors to the EEPROM of the sensor.

Then the software changes to the GO mode and displays the **RAW DATA** and the calibrated data in the main panel.

Please note that the values for **RED**, **GREEN**, and **BLUE** in the main panel approximately are equal to the value of SETVALUE.

You may also change the calibration factors **CF\_RED**, **CF\_GREEN**, **CF\_BLUE** manually by entering new values in the corresponding input fields. Please note that these factors are saved to the EEPROM by pressing **SEND CF**. **GET CF** reads the calibration factors that are currently saved in the EEPROM.

If pressing CALC CALIB FACTORS should not be successful, please follow the information provided in the pop-up windows.

Calibration only is completed successfully, if the following pop-up window is displayed:

CALIBRATION PASSED!
Calibration successful! Calibration factors were sent to the EEPROM of the sensor. GO mode will be activated.
<u>OK</u>



### 2.7.2 Offset calibration

To avoid an increase of the electronic offset when using the integral function (**INTEGRAL** parameter), this offset can be eliminated by way of offset calibration or zero-point calibration. The corresponding tab is password-protected to prevent inadvertent incorrect settings.

RED (	e.g. here: Double-clic right mouse	
SETVALUE	OF RAW DATA 500 E FOR R,G, B 000	RAW DATA
	B FACTORS	
CF_RED	1024	
CF_GREEN	1024	
CF_BLUE	1024	
SEN	ID CF	
GE	T CF	
* PASSWORD PANEL	_ X	1
ENTER PASSWORI		

Make sure that transmitter is off. POWER=0. Push CALCULATE OFFSET to detect the offset. Push SEND OFFSET to update the sensor.

DISPLAY FOR OFFSET RED 4069 DISPLAY FOR OFFSET GREEN 4062 DISPLAY FOR OFFSET BLUE 4057 CALCULATE OFFSET
EDIT BOX FOR OFFSET RED
EDIT BOX FOR OFFSET GREEN
EDIT BOX FOR OFFSET BLUE
SEND OFFSET
GET OFFSET

Offset calibration can be accessed by double-clicking with the right mouse button at any place between the individual elements in the **CALIBRATE** tab.

You will then be prompted to enter a password. The password is: mellon


Now please follow the instructions provided in the tab.

Now press **CALCULATE OFFSET**. The offset values for red, green, and blue should be approximately 4060 plus/minus 40.

The offset values can then be sent to the sensor by pressing **SEND OFFSET**.

**GET OFFSET** can be used to check whether the data have been sent.

### 2.8 Graphic display elements



27 TEN

TEMP

This display shows the temperature prevailing in the sensor housing. The display **DOES NOT** show degrees Centigrade or Fahrenheit.





#### delta C:]

This display (delta color) shows the deviation from a color hit, delta C corresponds with  $\Delta E$  that is calculated in a color measurement.

In **FIRST HIT** evaluation mode **delta C** represents the distance from a color hit. When no color has been hit, **delta C** is calculated in relation to the last valid color in the color table (depending on **MAXCOL-No**.).

In **BEST HIT** and **MIN DIST** evaluation mode **delta C** also represents the distance from a color hit. If, however, no color has been recognised, **delta C** assumes the value of -1.

In COL5 evaluation mode delta C is not calculated.

When the current intensity (INT or M) falls below the INTLIM parameter, delta C=-1 will be displayed.

In CALCULATION MODE X/Y INT and s/i M delta C represents the distance from the cylinder axis. In CALCULATION MODE X/Y/INT and s/i/M delta C represents the distance from the centre of the circle.




# 3. Short instructions fort he operation of color sensors with the SI-COLO3-Scope V6.4 software

These instructions describe how to perform quick teaching of the color sensors of SI-COLO3 series with the **SI-COLO3-Scope V6.4** software interface.

Basically there are 2 methods of teaching a color. These methods can be set with **CALCULATION MODE**. The **CALCULATION MODE = X/Y/INT (or s/i/M)** uses a color sphere in space with radius TOL. Contrary to this, the **CALCULATION MODE = X/Y INT (or s/i M)** uses a color cylinder in space with radius CTO or siTO and with height ITO or M.

The teach process is the same for both methods. Color evaluation according to  $s/i\ M$  uses the Lab calculation method.





The text below describes a teach process with **EVALUATION MODE = BEST HIT** and **CALCULATION MODE = X/Y/INT**.

#### Step 1:

Prior to the use of the software aids (graphic display of sensor signals) the sensor must be manually adjusted to the respective target or background as accurately as possible. The reference distance of the sensor to the target is defined in the data sheet of the respective sensor.


Please make sure that the sensor is properly connected and supplied with power. Furthermore the sensor head must be directed onto the brightest surface (paper, leather, glass, etc.) of the color to be taught. This is absolutely necessary for being able to set a suitable **POWER** value for the sensor.

#### Step 2:

Start the SI-COLO3-Scope V6.4 software. Please check whether the status line at the right bottom displays the "SI-COLO3 V6.4 RT:KWxx/xx " message.

**Info:** Moving the mouse cursor to a control element and clicking with the right mouse button displays a short info on the respective individual control element.

SI-COLO3-SCOPE V6.4				
	si-coi	LO3-Scope V6.4		
CONNECT       PARA       TEACH TABLE       GROUPS         RECORDER       CALIBRATE       TABLE ATTRIBUTES         POWER MODE       STATIC       Image: Constant of the state of the stat	SOURCE X 9 NT 0 INT 0 C-No: 0	X/Y/NT   10000- 9000- 8000- 7000- 5000- 5000- 5000- 2000- 1000- 0- 0 2000 400	• 000 2500 3000 3500	TEMP 0
THREE SIDES V	TEW	×// 4096-		



#### Step 3:

Please make sure that for the time being **RAM** and not **EEPROM** is selected for the data exchange with the sensor (RAM is a volatile memory in the sensor, i.e. the data will be lost when power is turned off. EEPROM is a non-volatile memory in the sensor, i.e. the data will not be lost when power is turned off.)

All the other parameters should be set as shown in the picture below. Press the tab **PARA** to show the parameters. (See the FILE function in the operating instructions.)

Now press the **GO** button. Data exchange between sensor and PC will then start. The contents for **RED**, **GREEN**, and **BLUE** that are diffusely reflected from the surface are represented as bars on the software interface. Set the POWER value in such a way that at least one of the three bars is in the upper third of its dynamic range, but none of them is in saturation.

**ATTENTION**: The sensor must be informed when you have changed the **POWER** value. Press the **SEND** button to send this information to the sensor. Check the bars by pressing **GO** again. Repeat this process until you have a suitable **POWER** value.

Optimally the three bars RED, GREEN, and BLUE should be at approximately the same level on white paper.

If the bars vary too much, you need to perform white light balancing.

(For white light balancing see the "SI-COLO3-Scope" operating instructions on the supplied CD.)

**Tip!** There is a trick for finding a suitable **POWER** value in no time at all. Set **POWER MODE = DYNAMIC**. The sensor then tries to find a suitable power value. Check this by pressing **GO**. Press **STOP** when the bars have "levelled out". Then press **GET**. The power value that was found now is shown in the **POWER** function field. Now set **POWER MODE = STATIC**, and press **SEND**.

🗮 SI-COLO3-SCOPE V6.4		
	SI-COLO3-Scope V6.4	
CONNECT       PARA       TEACH TABLE       GROUPS         RECORDER       CALIBRATE       TABLE ATTRIBUTES         POWER MODE       STATIC       Image: Calibrate in the imag	SOURCE X//INT X 10025- 2089 9000- Y 8000- 1091 107 2025 6000- 6000 5000- 5000- 4000- 1 3000- 255 1000- -25 2000 4000 6000 8000 10	TEMP 21
RAM     SEND     GO       EEPROM     GET     STOP		T:KW34/09



#### Step 4:

An  $\dot{X}$  and a Y coordinate as well as an intensity INT are calculated from the RED, GREEN, and BLUE data.  $X = (R^{*4095}) / (R+G+B)$   $Y = (G^{*4095}) / (R+G+B)$ INT = (R+G+B) / 3

Press the **GO** button once again to read out the current data.

Press **STOP** to stop the data exchange.


Now use the tab **TEACH TABLE** to switch to the TEACH TABLE.

Select a row under No .: to which the currently present color should be taught.

(ATTENTION: Only the rows marked with green numbers are evaluated by the sensor. If you want to teach more colors, use the **MAXCOL-No.** parameter to select how many colors you want to teach.)

Now press the **TEACH DATA TO** button. The calculated values for X, Y, and INT are transferred to the TEACH TABLE in the row that was selected under **No.:**.


The graphic display then shows a circle. This is the tolerance circle for the color. The radius of this circle can be set under **TOL** (tolerance). To change the TOL value, please double-click on the corresponding cell in the TEACH TABLE with the left mouse button. In the small graph the current intensity INT with the tolerance window set under No.: is displayed in turquoise.



Now press the **SEND** button again to inform the sensor about the taught color. Then activate the **GO** mode again. When the sensor recognises a row vector (color), the corresponding row number is visualised on the software interface under **C-No:**. A value of 255 means that none of the taught colors were recognised.

As you know the **X/Y/INT** mode uses a color sphere in space. To provide a better visual representation of this sphere, an additional panel is displayed here that shows the color sphere in a three-side view with the axes X/Y, X/INT, and Y/INT (see below).







A color is only recognised if its current coordinates lie in the tolerance circle.

#### Step 5:

For teaching additional colors please make sure that the sensor head is directed onto the respective color. Then repeat the procedure starting from step 4.

#### Step 6:

When you have taught all the channels, please select **EEPROM** and press **SEND** to save the data to the non-volatile memory of the sensor.

For the meaning and handling of the remaining parameters please refer to this manual.



### 4. Operation of the TEMPCOMP-Scope software

If a firmware update should go wrong and the temperature characteristics that are stored in the EEPROM should be lost, these characteristics must be created anew. For this purpose you will need a file with the corresponding data. This file can be obtained from your supplier.

To perform temperature compensation please start the corresponding **TEMPCOMP-Scope software** that is included on the supplied CD. Please make sure that you have a functioning sensor connection. It may be necessary to select the connection with **CONNECT**. Set the correct sensor under **SELECT SENSOR**, if this is not done automatically.

-** TEMPCOMP-Scope V1.4	
TEMPCOMP-Scope V1.4	
SELECT SENSOR SiColo3 V6.3 or higher CONNECT COMMUNICATION PORT 1 SI-COLO3 V6.4 RT:KW34/09	
GET EQUATION FROM DISK       SAVE EQUATION TO DISK         X^4       X^3       X^2       X       t         0.00000       -0.00090       -0.1159       12.2330       3516.1         0.00000       0.00140       -0.4002       20.2180       3424.9         0.00000       -0.00070       -0.2280       20.7000       3382.7         CALCULATE CURVES       SHOW RED       SHOW GREEN       SHOW BLUE         TEMP       0       R       3516       G       3425       B       3383	Selected sensor is SiColo3 or SiColo4 V6.3 or higher
SP R 3516 SP G 3424 SP B 3382	1425- 1368- 1312- 1256-
SHOW CF RED SHOW CF GREEN SHOW CF BLUE	1199- 1142- 1086- 1030-
SEND CF CURVE SAVING SUCCESS	973- 916- 860- 0 10 20 30 40 50 60 70 80 90 100

Step 1: Load the temperature compensation file that you have received from your supplier with **GET EQUATION FROM DISK**.

- Step 2: Press CALCULATE CURVES to display the data in the graph. The buttons SHOW RED, SHOW GREEN, and SHOW BLUE show the individual curves.
- Step 3: Select the sensor-internal operating temperature (not in °C) that the sensor has at an ambient temperature of 20°. The value should be included in the file designation.
- Step 4: Press CALCULATE CALIBRATION CURVES to calculate the mean straight line. The buttons SHOW CF RED, ... again show the individual curves.
- Step 5: Pressing the **SEND CF** button saves the mean straight lines in the EEPROM of the sensor.
- Step 6: Temperature compensation is successfully finished if the **SUCCESS** status message is then displayed.

#### Comment!

If you do not immediately have the temperature compensation file at hand, simply start the **TempComp-Scope software**. Establish a connection, if it is not already established, and simply press **SEND-CF**. The sensor then functions as before, but it is not temperature-compensated.



# 5. External triggering of the SI-COLO3 color sensor



External triggering is performed through pin no. 3 (grn) at the 8-pole socket of the SI-COLO3/PLC connection.

# TRIGGER CONT CONT SELF EXT1 EXT2 EXT3 EXT4


#### EXTERN:


First the external trigger mode must be set at the color sensor. For this purpose option EXT1, EXT2, EXT3, or EXT4 must be selected in the **TRIGGER** selection field.

# SEND

#### PLEASE NOTE:

The new setting is only activated at the sensor after a click on the SEND button!






Let's make sensors more individual

# DIRECT

In the DIRECT mode (OUT DIRECT HI or OUT DIRECT LO) the maximum numbers of colors to be taught is 4 (color no. 0, 1, 2, 3).

If **DIRECT HI** is activated, the specially digital output is set to HI, while the other 3 are set to LO. If the current color does not correspond with any of the teach-in colors, color C-No = 0 is set, i.e. all digital outputs are set to LOW (no LED is lighting).





# 7. Connector assignment of the SI-COLO3 color sensor

# Connection of SI-COLO3 to PC:

5-ŗ	oole female connector (type Bind SI-COLO3/PC-RS232	er 712)
Pin No.:		Assignment:
1		0V (GND)
2		TxD
3		RxD
4		Not connected
5		Not connected

# Connection of SI-COLO3 to PLC:

8-pole female connector (type Binder 712) <i>SI-COLO3/PLC</i>				
Pin No.:	Color:	Assi	gnment:	
1	White	0V	(GND)	
2	Brown	Brown +24V		
3	Green	INO		
4	Yellow	OUT0 (Digital 0: Type 0	1V, Digital 1: Type -	+Ub – 10%)
5	Grey	OUT1 (Digital 0: Type 0	1V, Digital 1: Type -	+Ub – 10%)
6	Pink	OUT2 (Digital 0: Type 0	1V, Digital 1: Type -	+Ub – 10%)
7	Blue	Blue OUT3 (Digital 0: Type 0 1V, Digital 1: Type +Ub -		+Ub – 10%)
8	Red	Not c	onnected	

# 8. RS232 communication protocol

# RS232 communication protocol PC ⇔ SI-COLO3 Sensor (SI-COLO3-Scope V6.4)

- Standard RS232 serial interface without hardware-handshake

- 3-wire: GND, TX0, RX0

- Speed: 19200 baud factory setting, can be changed (example 190) to 9600, 19200, 38400, 57600, 115200 8 data-bits, no parity-bit, 1 stop-bit in binary mode, us (unsigned), MSB (most significant byte) first.

The control device (PC or PLC) has to send a data frame of 18 words to the Sensor. All bytes must be transmitted in binary format (us, MSB). The meaning of the parameters is described in the software manual. Info: 1 word = 2 bytes

Method:

The hardware is permanently reading (polling) the incoming byte at the RS232 connection. If the incoming word is 0x0055 (synch-word), then the 2. word (order-word) is read in, after this, 16 words (parameters) will be read. After reading in the completely data frame, the Sensor executes the order which is coded at the 2. word (order-word).

	Format of the data frame:		
Word No.	Format	Meaning	Comment:
1	Word	sync-word = 0x0055	hex-code 0x0055, binary: 0000 0000 0101 0101, synchronisation word
2	Word	ORDER NUMBER	order word
3	Word	Para POWER	LED intensity (01000) Attention intensity in thousendth!
4	Word	Para POWER MODE	LED mode: STATIC, DYNAMIC coded to (0,1)
5	Word	Para AVERAGE	Signal averaging 1, 2, 4, 8, 16, 32, 64, 128, 256, 512, 1024, 2048, 4096, 8192, 16384 or 32768
6	Word	Para EVALUATION MODE	Evaluation mode: FIRST HIT, BEST HIT, MIN DIST, COL4 coded to (0,1,2,3)
7	Word	Para HOLD[ms]	Hold time 0,1,2,3,5,10,50 or 100ms
8	Word	Para INTLIM	Intensity limit (04095)
9	Word	Para MAXCOL-No.	Number of the colours (1,2,3,,31)
10	Word	Para OUTMODE	Function of the digital output: direct/HI, binary, direct/LO coded to (0,1,2)
11	Word	Para TRIGGER	Trigger mode: CONT,SELF,EXT1,EXT2,EXT3,EXT4 coded to (0,1,2,3,4,5)
12	Word	Para EXTEACH	External teach mode: OFF, ON, STAT1, DYN1 coded to (0,1,2,3)
13	Word	Para CALCULATION MODE	Calculation mode: X/Y INT, s/i M, X/Y/INT, s/i/M coded to (0,1,2,3)
14	Word	Para DYN WIN LO	Low limit for dynamic window when POWERMODE=dynamic (04095)
15	Word	Para DYN WIN HI	High limit for dynamic window when POWERMODE=dynamic (04095)
16	Word	Para COLOR GROUPS	Color groups enable: OFF, ON coded to (0,1)
19	Word	Para INTEGRAL	Signal integration (1250)
18	Word	free	Must be sent as dummy (e.g. value 0)

Value	ORDER NUMBER (parameter by	/te no. 2)
0	nop	no operation
1	Save parameter from PC into RAM	Cf. Example 1
2	Save one selectable row of TEACH TABLE into RAM	Cf. Example 2
3	Send parameter from RAM to PC	Cf. Example 3
4	Send one selectable Row of TEACH TABLE from RAM to PC	Cf. Example 4
5	Send data from RAM to PC	Cf. Example 5
6	Save parameter from RAM to EEPROM	Cf. Example 6
7	Send connection OK to PC	Cf. Example 7
8	Load Parameter from EEPROM to RAM	Cf. Example 8
20	Send line ok = 0x00AA, 0x0014, 0x00AA, 15 Dummies to PC	Cf. Example 20
30	Save Calibration factors RED, GREEN, BLUE from PC into EEPROM	Cf. Example 30
31	Save Offset values for RED, GREEN, BLUE from PC into EEPROM	Cf. Example 31
32	Send Calibration factors RED, GREEN BLUE from EEPROM to PC	Cf. Example 32
50	Start or Stop an automatic send of a data frame after trigger	Cf. Example 50
190	Change baud rate	CF.Example190



# Example 1: DATA FRAME with ORDER NUMBER = 1:

ORDER NUMBER (second word = 1): WRITE parameters from PC into RAM of the sensor! The completely data frame = 18 words must be sent to the sensor hardware in binary form (sync-word / order-word / 16 parameter words).

#### DATA FRAME PC → Sensor (18 WORDS)

0x0055	SYNCWORD
1	ORDER-WORD
200	POWER
0	POWER MODE
1024	AVERAGE
0	EVALUATION MODE
10	HOLD
10	INTLIM
5	MAXCOL-No.
0	OUTMODE
0	TRIGGER
0	EXTEACH
0	CALCULATION MODE
3000	DYN WIN LO
3500	DYN WIN HI
0	COLOR GROUPS
1	INTEGRAL
0	DUMMY

0x00AA	SYNCWORD	
1	ORDER-WORD	
200	POWER	
0	POWER MODE	
1024	AVERAGE	
0	EVALUATION MODE	
10	HOLD	
10	INTLIM	
5	MAXCOL-No.	
0	OUTMODE	
0	TRIGGER	
0	EXTEACH	
0	CALCULATION MODE	
3000	DYN WIN LO	
3500	DYN WIN HI	
0	COLOR GROUPS	
1	INTEGRAL	
0	DUMMY	

### Example 3: DATA FRAME with ORDER NUMBER = 3:

ORDER NUMBER (second word = 3): READ parameters out of sensor-RAM memory! The same frame as example 1 must be sent to the sensor except of the order word that must be 3. The values for

the parameters must be sent as Dummies.

The complete DATA FRAME which is responded by the sensor is 18 words.

#### DATA FRAME PC → Sensor (18 WORDS) DATA FRAME Sensor → PC (18 WORDS)

	SYNC-WORD
0x00AA	
3	ORDER-WORD
200	POWER
0	POWER MODE
1024	AVERAGE
0	EVALUATION MODE
10	HOLD
10	INTLIM
5	MAXCOL-No.
0	OUTMODE
0	TRIGGER
0	EXTEACH
0	CALCULATION MODE
3000	DYN WIN LO
3500	DYN WIN HI
0	COLOR GROUPS
1	INTEGRAL
0	DUMMY



# Example 2: DATA FRAME with ORDER NUMBER = 2:

ORDER NUMBER (second word = 2): WRITE one selectable row (vector) of TEACH TABLE into RAM of the sensor!

The completely data frame = 18 words must be sent to the sensor in binary form. (sync-word / order-word / ROW-NO / parameter words = vector, dummies). Fill unused words of the TEACH VECTOR by value word=1 in binary form.

#### CALCMODE = X/Y INT respectively s/i M

#### DATA FRAME PC → Sensor (18 WORDS)

#### DATA FRAME Sensor → PC (18 WORDS)

0x0055	SYNCWORD
2	ORDER-WORD
0	ROW-No. (014)
1200	X respectively s
1500	Y respectively i
200	CTO respectively siTO
2000	INT respectively M
200	ITO respectively MTO
0	GROUP (COLOR Group)
1	DUMMY

0x00AA	SYNC-WORD
2	ORDER-WORD
0	ROW-No. (014)
1200	X respectively s
1500	Y respectively i
200	CTO respectively siTO
2000	INT respectively M
200	ITO respectively MTO
0	GROUP (COLOR Group)
1	DUMMY

# CALCMODE = X/Y/NT respectively s/i/M DATA FRAME PC → Sensor (18 WORDS)

0.0055	
0x0055	SYNCWORD
2	ORDER-WORD
0	ROW-No. (014)
1200	X respectively s
1500	Y respectively i
2000	INT respectively M
200	TOL
1	DUMMY
0	GROUP (COLOR Group)
1	DUMMY

#### SYNC-WORD 0x00AA ORDER-WORD 2 0 ROW-No. (0...14) 1200 X respectively s 1500 Y respectively i 2000 INT respectively M 200 TOL DUMMY 1 GROUP (COLOR Group) 0 1 DUMMY DUMMY 1 DUMMY 1 1 DUMMY DUMMY 1 DUMMY 1 DUMMY 1 DUMMY 1 DUMMY



# Example 4: DATA FRAME with ORDER NUMBER = 4:

ORDER NUMBER (second word = 4): READ one selectable row (vector) from RAM of the sensor! The same frame as example 2 must be sent to the sensor except of the order word that must be **4**. The values for the parameters must be sent as Dummies. The complete DATA FRAME which is responded by the sensor is 18 words.

#### DATA FRAME PC → Sensor (18 WORDS) DATA FRAME Sensor → PC (18 WORDS)

**CALCMODE = X/Y INT** respectively s/i M

CALCMODE = X/Y/NT respectively s/i/M

0x00AA	SYNC-WORD	
4	ORDER-WORD	
0	ROW-No. (014)	
1200	X respectively s	
1500	Y respectively i	
200	CTO respectively siTO	
2000	INT respectively M	
200	ITO respectively MTO	
0	GROUP (COLOR Group)	
1	DUMMY	

0x00AA	SYNC-WORD
4	ORDER-WORD
0	ROW-No. (014)
1200	X respectively s
1500	Y respectively i
2000	INT respectively M
200	TOL
0	DUMMY
0	GROUP (COLOR Group)
1	DUMMY

# Example 5: DATA FRAME with ORDER NUMBER = 5:

ORDER NUMBER (second word = 5): READ DATA. Parameters must be sent for a constant parameter frame as dummies. At order word **5** they do not affect the RAM or EEPROM.

#### DATA FRAME PC → Sensor (18 WORDS)

0x0055	SYNCWORD
5	ORDER-WORD
0	DUMMY

0x00AA	
5	
R	
G	
В	
Х	
Y	
INT	
C-No.	
RAW R	
RAW G	
RAW B	
TEMP	
GRP	
TRIGGER	
delta C	
DUMMY	
DUMMY	



# Example 6: DATA FRAME with ORDER NUMBER = 6:

ORDER NUMBER (second word = 6): SAVE parameters from RAM to EEPROM of the sensor! The complete data frame = 18 words must be sent to the sensor in binary form (sync-word / order-word / 16 parameter words).

#### DATA FRAME PC → Sensor (18 WORDS)

0x0055	SYNCWORD
6	ORDER-WORD
0	DUMMY

After sending this data frame, the sensor saves all the parameters and teach vectors from its RAM (volatile memory) to its EEPROM (non volatile memory).

**ATTENTION**: The right parameters and teach vectors must be in the RAM of the sensor. To save the parameters and teach vectors into RAM see **Example 1** and **Example 2**.

After completing the sensor writes back an echo of the same frame.

0x00AA	SYNC-WORD
6	ORDER-WORD
0	DUMMY



# Example 7: DATA FRAME with ORDER NUMBER = 7:

ORDER NUMBER (second word = 7): SEND CONNECTION OK from the sensor! Cf. example 1: Send the same DATA FRAME but with ORDER NUMBER 7 to the sensor. The sensor will reply with 18 words which tell the version of the sensor.

### Example 8: DATA FRAME with ORDER NUMBER = 8:

ORDER NUMBER (second word = 8): Load parameters from EEPROM to RAM of the sensor! The complete data frame = 18 words must be sent to the sensor in binary form (sync-word / order-word / 16 parameter words).

#### DATA FRAME PC → Sensor (18 WORDS)

0x0055	SYNCWORD
8	ORDER-WORD
0	DUMMY

After sending this data frame, the sensor loads all the parameters and teach vectors from it's EEPROM (non volatile memory) to it's RAM (volatile memory).

**ATTENTION**: The EEPROM parameters must be load first to the RAM to read it from the sensor. To get the parameters and teach vectors from RAM see **Example3** and **Example4**.

After completing the sensor writes back an echo of the same frame.

0x00AA	SYNC-WORD
8	ORDER-WORD
0	DUMMY



# Example 20: DATA FRAME with ORDER NUMBER = 20:

ORDER NUMBER (second word = 20): SEND LINE OK from the sensor to PC! Cf. example 1: Send the same DATA FRAME but with ORDER NUMBER 20 to the sensor. The sensor will reply with the same18 words but with SYNC-WORD=0x00AA which tell that there is a connection.

# Example 30: DATA FRAME with ORDER NUMBER = 30:

ORDER NUMBER (second word = 30): Write calibration factors RED, GREEN, BLUE from PC into EEPROM! The completely data frame = 18 words must be sent to the sensor hardware in binary form (sync-word / order-word / 16 parameter words).

#### DATA FRAME PC → Sensor (18 WORDS)

0x0055	SYNCWORD
30	ORDER-WORD
VALUE	CF RED
VALUE	CF GREEN
VALUE	CF BLUE
0	DUMMY

0x00AA	SYNCWORD
30	ORDER-WORD
VALUE	CF RED
VALUE	CF GREEN
VALUE	CF BLUE
VALUE	OFFSET RED
VALUE	OFFSET GREEN
VALUE	OFFSET BLUE
0	DUMMY



# Example 31: DATA FRAME with ORDER NUMBER = 31:

ORDER NUMBER (second word = 31): Write calibration factors Offset RED, Offset GREEN, Offset BLUE from PC into EEPROM!

The completely data frame = 18 words must be sent to the sensor hardware in binary form (sync-word / order-word / 16 parameter words).

#### DATA FRAME PC → Sensor (18 WORDS)

0x0055	SYNCWORD
31	ORDER-WORD
VALUE	OFFSET RED
VALUE	OFFSET GREEN
VALUE	OFFSET BLUE
0	DUMMY

0x00AA	SYNCWORD
31	ORDER-WORD
VALUE	CF RED
VALUE	CF GREEN
VALUE	CF BLUE
VALUE	OFFSET RED
VALUE	OFFSET GREEN
VALUE	OFFSET BLUE
0	DUMMY



# Example 32: DATA FRAME with ORDER NUMBER = 32:

ORDER NUMBER (second word = 32): READ calibration factor RED, GREEN, BLUE and Offset RED, Offset GREEN, Offset BLUE from the EEPROM of the sensor! The same frame as example 30 must be sent to the sensor except of the order word that must be 32.

The values do not affect the sensor.

The complete DATA FRAME which is responded by the sensor is 18 words.

#### DATA FRAME PC → Sensor (18 WORDS) DATA FRAME Sensor → PC (18 WORDS)

0x00AA	SYNC-WORD
32	ORDER-WORD
VALUE	CF RED
VALUE	CF GREEN
VALUE	CF BLUE
VALUE	OFFSET RED
VALUE	OFFSET GREEN
VALUE	OFFSET BLUE
0	DUMMY

### Example 50: DATA FRAME with ORDER NUMBER = 50:

ORDER NUMBER (second word = 50): Start or Stop an automatic send of a data frame after a trigger. The complete data frame = 18 words must be sent to the Sensor hardware in binary form (sync-word / order-word / 16 parameter words).

#### DATA FRAME PC → Sensor (18 WORDS)

0x0055	SYNC-WORD
50	ORDER-WORD
0	0=autosend off, 1=autosend on
0	DUMMY

After activation an automatic send (autosend=1) the sensor writes after each trigger a dataframe. Cf. DATA FRAME Sensor  $\rightarrow$  PC (18 WORDS) in Example 5.



# Example 190: DATA FRAME with ORDER NUMBER = 190:

ORDER NUMBER (second word = 190): Write new baud rate to sensor. Attention! New baud rate is only in the RAM. To store the new baud rate to EEPROM refer to example 6.

baud rate is coded to:		
0	9600 Bit/s	
1	19200 Bit/s	
2	38400 Bit/s	
3	57600 Bit/s	
4	115200 Bit/s	

The completely data frame = 18 words must be sent to the sensor hardware in binary form **with old baud rate** (sync-word / order-word / 16 parameter words).

### DATA FRAME PC → Sensor (18 WORDS)

0x0055	SYNCWORD
190	ORDER-WORD
3	new baud rate 57600 Bit/s
0	DUMMY

DATA FRAME Sensor  $\rightarrow$  PC (18 WORDS) comes also with old baud rate.

0x00AA	SYNCWORD
190	ORDER-WORD
3	new baud rate 57600 Bit/s
0	DUMMY

FROM now the sensor works with the new baud rate.